#### Added in API level 1

Summary: Nested Classes | Constants | Methods | Inherited Methods | [Expand All]

# SensorManager

public abstract class SensorManager
extends Object

#### java.lang.Object

SensorManager lets you access the device's sensors. Get an instance of this class by calling Context.getSystemService() with the argument SENSOR\_SERVICE.

Always make sure to disable sensors you don't need, especially when your activity is paused. Failing to do so can drain the battery in just a few hours. Note that the system will *not* disable sensors automatically when the screen turns off.

Note: Don't use this mechanism with a Trigger Sensor, have a look at TriggerEventListener. TYPE\_SIGNIFICANT\_MOTION is an example of a trigger sensor.

```
public class SensorActivity extends Activity implements SensorEventListener {
   private final SensorManager mSensorManager;
   private final Sensor mAccelerometer;

public SensorActivity() {
    mSensorManager = (SensorManager)getSystemService(SENSOR_SERVICE);
   mAccelerometer = mSensorManager.getDefaultSensor(Sensor.TYPE_ACCELEROMETER);
}

protected void onResume() {
   super.onResume();
}
```

```
mSensorManager.registerListener(this, mAccelerometer, SensorManager.SENSOR_DELAY_NORMAL);
}

protected void onPause() {
    super.onPause();
    mSensorManager.unregisterListener(this);
}

public void onAccuracyChanged(Sensor sensor, int accuracy) {
    public void onSensorChanged(SensorEvent event) {
    }
}
```

See also:

SensorEventListener

SensorEvent

Sensor

# Summary

| Nested | Nested classes  |  |
|--------|---|--|
| class  | SensorManager.DynamicSensorCallback   |  |
|        | Used for receiving notifications from the SensorManager when dynamic sensors are connected or disconnected. |  |

| Constants |  |
|-----------|--|
| int       | AXIS_MINUS_X see remapCoordinateSystem(float[], int, int, float[]) |
| int       | AXIS_MINUS_Y   |

|       | see remapCoordinateSystem(float[], int, int, float[])              |
|-------|--|
| int   | AXIS_MINUS_Z   |
|       | see remapCoordinateSystem(float[], int, int, float[])              |
| int   | AXIS_X   |
|       | see remapCoordinateSystem(float[], int, int, float[])              |
| int   | AXIS_Y   |
|       | see remapCoordinateSystem(float[], int, int, float[])              |
| int   | AXIS_Z   |
|       | see remapCoordinateSystem(float[], int, int, float[])              |
| int   | DATA_X   |
|       | This constant was deprecated in API level 3. use Sensor instead.   |
| int   | DATA_Y   |
|       | This constant was deprecated in API level 3. use Sensor instead.   |
| int   | DATA_Z   |
|       | This constant was deprecated in API level 3. use Sensor instead.   |
| float | GRAVITY_DEATH_STAR_I   |
|       | Gravity (estimate) on the first Death Star in Empire units (m/s^2) |
| float | GRAVITY_EARTH  |
|       | Earth's gravity in SI units (m/s^2)                                |
| float | GRAVITY_JUPITER  |
|       | Jupiter's gravity in SI units (m/s^2)                              |
| float | GRAVITY_MARS   |
|       | Mars' gravity in SI units (m/s^2)                                  |
| float | GRAVITY_MERCURY  |
|       | Mercury's gravity in SI units (m/s^2)                              |
| float | GRAVITY_MOON   |
|       | The Moon's gravity in SI units (m/s^2)                             |
|       |  |

| float | GRAVITY_NEPTUNE  Neptune's gravity in SI units (m/s^2)  |
|-------|---|
| float | GRAVITY_PLUTO Pluto's gravity in SI units (m/s^2)       |
| float | GRAVITY_SATURN Saturn's gravity in SI units (m/s^2)     |
| float | GRAVITY_SUN Sun's gravity in SI units (m/s^2)           |
| float | GRAVITY_THE_ISLAND Gravity on the island                |
| float | GRAVITY_URANUS Uranus' gravity in SI units (m/s^2)      |
| float | GRAVITY_VENUS  Venus' gravity in SI units (m/s^2)       |
| float | LIGHT_CLOUDY luminance under a cloudy sky in lux        |
| float | LIGHT_FULLMOON luminance at night with full moon in lux |
| float | LIGHT_NO_MOON luminance at night with no moon in lux    |
| float | LIGHT_OVERCAST luminance under an overcast sky in lux   |
| float | LIGHT_SHADE luminance in shade in lux                   |
| float | LIGHT_SUNLIGHT luminance of sunlight in lux             |
| float | LIGHT_SUNLIGHT_MAX                                      |

| float LIGHT_SUNRISE luminance at sunrise in lux  float MAGNETIC_FIELD_EARTH_MAX Maximum magnetic field on Earth's surface  float MAGNETIC_FIELD_EARTH_MIN Minimum magnetic field on Earth's surface  float PRESSURE_STANDARD_ATMOSPHERE Standard atmosphere, or average sea-level pressure in hPa (millibar) |
|--|
| Maximum magnetic field on Earth's surface  float MAGNETIC_FIELD_EARTH_MIN    Minimum magnetic field on Earth's surface  float PRESSURE_STANDARD_ATMOSPHERE   |
| Minimum magnetic field on Earth's surface  float PRESSURE_STANDARD_ATMOSPHERE  |
|  |
|  |
| int RAW_DATA_INDEX This constant was deprecated in API level 3. use Sensor instead.  |
| int RAW_DATA_X This constant was deprecated in API level 3. use Sensor instead.  |
| int RAW_DATA_Y This constant was deprecated in API level 3. use Sensor instead.  |
| int RAW_DATA_Z This constant was deprecated in API level 3. use Sensor instead.  |
| int SENSOR_ACCELEROMETER  This constant was deprecated in API level 3. use Sensor instead.   |
| int SENSOR_ALL  This constant was deprecated in API level 3. use Sensor instead.   |
| int SENSOR_DELAY_FASTEST get sensor data as fast as possible   |
| int SENSOR_DELAY_GAME rate suitable for games  |
| int SENSOR_DELAY_NORMAL rate (default) suitable for screen orientation changes   |

| int | SENSOR_DELAY_UI rate suitable for the user interface   |
|-----|--|
| int | SENSOR_LIGHT  This constant was deprecated in API level 3. use Sensor instead.   |
| int | SENSOR_MAGNETIC_FIELD  This constant was deprecated in API level 3. use Sensor instead.  |
| int | SENSOR_MAX This constant was deprecated in API level 3. use Sensor instead.  |
| int | SENSOR_MIN This constant was deprecated in API level 3. use Sensor instead.  |
| int | SENSOR_ORIENTATION  This constant was deprecated in API level 3. use Sensor instead.   |
| int | SENSOR_ORIENTATION_RAW  This constant was deprecated in API level 3. use Sensor instead.   |
| int | SENSOR_PROXIMITY  This constant was deprecated in API level 3. use Sensor instead.   |
| int | SENSOR_STATUS_ACCURACY_HIGH This sensor is reporting data with maximum accuracy  |
| int | SENSOR_STATUS_ACCURACY_LOW  This sensor is reporting data with low accuracy, calibration with the environment is needed  |
| int | SENSOR_STATUS_ACCURACY_MEDIUM  This sensor is reporting data with an average level of accuracy, calibration with the environment may improve the readings  |
| int | SENSOR_STATUS_NO_CONTACT  The values returned by this sensor cannot be trusted because the sensor had no contact with what it was measuring (for example, the heart rate monitor is not in contact with the user). |
| int | SENSOR_STATUS_UNRELIABLE  The values returned by this sensor cannot be trusted, calibration is needed or the environment doesn't allow readings  |

| int   | SENSOR_TEMPERATURE  This constant was deprecated in API level 3. use Sensor instead. |
|-------|--|
| int   | SENSOR_TRICORDER  This constant was deprecated in API level 3. use Sensor instead.   |
| float | STANDARD_GRAVITY Standard gravity (g) on Earth.                                      |

| Public methods         |   |
|------------------------|---|
| boolean                | cancelTriggerSensor(TriggerEventListener listener, Sensor sensor)  Cancels receiving trigger events for a trigger sensor.   |
| boolean                | flush(SensorEventListener listener) Flushes the FIFO of all the sensors registered for this listener.   |
| static<br>float        | getAltitude(float p0, float p)  Computes the Altitude in meters from the atmospheric pressure and the pressure at sea level.  |
| static<br>void         | <pre>getAngleChange(float[] angleChange, float[] R, float[] prevR) Helper function to compute the angle change between two rotation matrices.</pre>                               |
| Sensor                 | getDefaultSensor(int type) Use this method to get the default sensor for a given type.  |
| Sensor                 | getDefaultSensor(int type, boolean wakeUp) Return a Sensor with the given type and wakeUp properties.   |
| List <sensor></sensor> | getDynamicSensorList(int type) Use this method to get a list of available dynamic sensors of a certain type.  |
| static<br>float        | getInclination(float[] I)  Computes the geomagnetic inclination angle in radians from the inclination matrix I returned by getRotationMatrix(float[], float[], float[], float[]). |
| static<br>float[]      | getOrientation(float[] R, float[] values)  Computes the device's orientation based on the rotation matrix.  |

| static<br>void         | getQuaternionFromVector(float[] Q, float[] rv) Helper function to convert a rotation vector to a normalized quaternion.   |
|------------------------|---|
| static                 | <pre>getRotationMatrix(float[] R, float[] I, float[] gravity, float[] geomagnetic)</pre>  |
| boolean                | Computes the inclination matrix I as well as the rotation matrix R transforming a vector from the device coordinate system to the world's coordinate system which is defined as a direct orthonormal basis, where:                        |
|                        | • X is defined as the vector product Y.Z (It is tangential to the ground at the device's current location and roughly points East).   |
| static<br>void         | getRotationMatrixFromVector(float[] R, float[] rotationVector)  Helper function to convert a rotation vector to a rotation matrix.  |
| List <sensor></sensor> | getSensorList(int type) Use this method to get the list of available sensors of a certain type.   |
| int                    | getSensors()  This method was deprecated in API level 3. This method is deprecated, use getSensorList(int) instead  |
| boolean                | isDynamicSensorDiscoverySupported()  Tell if dynamic sensor discovery feature is supported by system.   |
| void                   | registerDynamicSensorCallback (SensorManager.DynamicSensorCallback callback) Add a DynamicSensorCallback to receive dynamic sensor connection callbacks.  |
| void                   | registerDynamicSensorCallback(SensorManager.DynamicSensorCallback callback, Handler handler) Add a DynamicSensorCallback to receive dynamic sensor connection callbacks.  |
| boolean                | registerListener(SensorEventListener listener, Sensor sensor, int samplingPeriodUs) Registers a SensorEventListener for the given sensor at the given sampling frequency.   |
| boolean                | registerListener(SensorEventListener listener, Sensor sensor, int samplingPeriodUs, int maxReportLatencyUs) Registers a SensorEventListener for the given sensor at the given sampling frequency and the given maximum reporting latency. |
| boolean                | registerListener(SensorEventListener listener, Sensor sensor, int samplingPeriodUs, Handler handler) Registers a SensorEventListener for the given sensor.  |
| boolean                | registerListener(SensorListener listener, int sensors)  This method was deprecated in API level 3. This method is deprecated, use registerListener(SensorEventListener, Sensor, int) instead.   |
| boolean                | registerListener(SensorListener listener, int sensors, int rate)  |

|                   | This method was deprecated in API level 3. This method is deprecated, use registerListener(SensorEventListener, Sensor, int) instead.  |
|-------------------|--|
| boolean           | registerListener(SensorEventListener listener, Sensor sensor, int samplingPeriodUs, int maxReportLatencyUs, Handler handler) Registers a SensorEventListener for the given sensor at the given sampling frequency and the given maximum reporting latency. |
| static<br>boolean | remapCoordinateSystem(float[] inR, int X, int Y, float[] outR)  Rotates the supplied rotation matrix so it is expressed in a different coordinate system.  |
| boolean           | requestTriggerSensor(TriggerEventListener listener, Sensor sensor) Requests receiving trigger events for a trigger sensor.   |
| void              | unregisterDynamicSensorCallback (SensorManager.DynamicSensorCallback callback) Remove a DynamicSensorCallback to stop sending dynamic sensor connection events to that callback.   |
| void              | unregisterListener(SensorEventListener listener) Unregisters a listener for all sensors.   |
| void              | unregisterListener(SensorEventListener listener, Sensor sensor) Unregisters a listener for the sensors with which it is registered.  |
| void              | unregisterListener(SensorListener listener)  This method was deprecated in API level 3. This method is deprecated, use unregisterListener(SensorEventListener) instead.  |
| void              | unregisterListener(SensorListener listener, int sensors)  This method was deprecated in API level 3. This method is deprecated, use unregisterListener(SensorEventListener, Sensor) instead.   |

#### Inherited methods

From class java.lang.Object

# Constants

int AXIS\_MINUS\_X

see remapCoordinateSystem(float[], int, int, float[])

Constant Value: 129 (0x00000081)

# AXIS\_MINUS\_Y

int AXIS\_MINUS\_Y

see remapCoordinateSystem(float[], int, int, float[])

Constant Value: 130 (0x00000082)

### AXIS\_MINUS\_Z

int AXIS\_MINUS\_Z

see remapCoordinateSystem(float[], int, int, float[])

Constant Value: 131 (0x00000083)

AXIS\_X

int AXIS\_X

see remapCoordinateSystem(float[], int, int, float[])

Constant Value: 1 (0x00000001)

Added in API level 3

Added in API level 3

int AXIS\_Y

see remapCoordinateSystem(float[], int, int, float[])

Constant Value: 2 (0x00000002)

AXIS\_Z

int AXIS\_Z

see remapCoordinateSystem(float[], int, int, float[])

Constant Value: 3 (0x00000003)

DATA\_X

int DATA\_X

This constant was deprecated in API level 3.

use Sensor instead.

Index of the X value in the array returned by onSensorChanged(int, float[])

Constant Value: 0 (0x00000000)

Added in API level 3

Added in API level 1

DATA\_Y

This constant was deprecated in API level 3.

use Sensor instead.

Index of the Y value in the array returned by onSensorChanged(int, float[])

Constant Value: 1 (0x00000001)

DATA Z

int DATA\_Z

This constant was deprecated in API level 3.

use Sensor instead.

Index of the Z value in the array returned by onSensorChanged(int, float[])

Constant Value: 2 (0x00000002)

### GRAVITY\_DEATH\_STAR\_I

float GRAVITY\_DEATH\_STAR\_I

Gravity (estimate) on the first Death Star in Empire units (m/s^2)

Constant Value: 3.5303614E-7

Added in API level 1

Added in API level 1

**GRAVITY\_EARTH** 

Added in API level 1

float GRAVITY\_EARTH

Earth's gravity in SI units (m/s^2)

Constant Value: 9.80665

GRAVITY\_JUPITER

Added in API level 1

float GRAVITY\_JUPITER

Jupiter's gravity in SI units (m/s^2)

Constant Value: 23.12

#### GRAVITY\_MARS

float GRAVITY\_MARS

Mars' gravity in SI units (m/s^2)

Constant Value: 3.71

Added in API level 1

# GRAVITY\_MERCURY

float GRAVITY\_MERCURY

Mercury's gravity in SI units (m/s^2)

Constant Value: 3.7

GRAVITY\_MOON

Added in API level 1

float GRAVITY\_MOON

The Moon's gravity in SI units (m/s^2)

Constant Value: 1.6

### **GRAVITY\_NEPTUNE**

float GRAVITY\_NEPTUNE

Neptune's gravity in SI units (m/s^2)

Constant Value: 11.0

### **GRAVITY\_PLUTO**

float GRAVITY\_PLUTO

Pluto's gravity in SI units (m/s^2)

Constant Value: 0.6

# GRAVITY\_SATURN

float GRAVITY\_SATURN

Saturn's gravity in SI units (m/s^2)

Constant Value: 8.96

Added in API level 1

Added in API level 1

GRAVITY\_SUN

Added in API level 1

float GRAVITY\_SUN

Sun's gravity in SI units (m/s^2)

Constant Value: 275.0

### GRAVITY\_THE\_ISLAND

float GRAVITY\_THE\_ISLAND

Gravity on the island

Constant Value: 4.815162

# GRAVITY\_URANUS

float GRAVITY\_URANUS

Uranus' gravity in SI units (m/s^2)

Constant Value: 8.69

# GRAVITY\_VENUS

float GRAVITY\_VENUS

Venus' gravity in SI units (m/s^2)

Constant Value: 8.87

Added in API level 1

Added in API level 1

LIGHT\_CLOUDY

Added in API level 1

float LIGHT\_CLOUDY

luminance under a cloudy sky in lux

Constant Value: 100.0

### LIGHT\_FULLMOON

float LIGHT\_FULLMOON

luminance at night with full moon in lux

Constant Value: 0.25

### LIGHT\_NO\_MOON

float LIGHT\_NO\_MOON

luminance at night with no moon in lux

Constant Value: 0.001

# LIGHT\_OVERCAST

float LIGHT\_OVERCAST

luminance under an overcast sky in lux

Constant Value: 10000.0

Added in API level 1

Added in API level 1

LIGHT\_SHADE

Added in API level 1

float LIGHT\_SHADE

luminance in shade in lux

Constant Value: 20000.0

### LIGHT\_SUNLIGHT

float LIGHT\_SUNLIGHT

luminance of sunlight in lux

Constant Value: 110000.0

# LIGHT\_SUNLIGHT\_MAX

float LIGHT\_SUNLIGHT\_MAX

Maximum luminance of sunlight in lux

Constant Value: 120000.0

### LIGHT\_SUNRISE

float LIGHT\_SUNRISE

luminance at sunrise in lux

Constant Value: 400.0

Added in API level 1

Added in API level 1

float MAGNETIC\_FIELD\_EARTH\_MAX

Maximum magnetic field on Earth's surface

Constant Value: 60.0

#### MAGNETIC\_FIELD\_EARTH\_MIN

float MAGNETIC\_FIELD\_EARTH\_MIN

Minimum magnetic field on Earth's surface

Constant Value: 30.0

# PRESSURE\_STANDARD\_ATMOSPHERE

float PRESSURE\_STANDARD\_ATMOSPHERE

Standard atmosphere, or average sea-level pressure in hPa (millibar)

Constant Value: 1013.25

# RAW\_DATA\_INDEX

int RAW\_DATA\_INDEX

This constant was deprecated in API level 3.

use Sensor instead.

Added in API level 1

Added in API level 9

Offset to the untransformed values in the array returned by onSensorChanged(int, float[])

Constant Value: 3 (0x00000003)

#### RAW\_DATA\_X

Added in API level 1

int RAW\_DATA\_X

This constant was deprecated in API level 3.

use Sensor instead.

Index of the untransformed X value in the array returned by onSensorChanged(int, float[])

Constant Value: 3 (0x00000003)

#### RAW\_DATA\_Y

Added in API level 1

int RAW\_DATA\_Y

This constant was deprecated in API level 3.

use Sensor instead.

Index of the untransformed Y value in the array returned by onSensorChanged(int, float[])

Constant Value: 4 (0x00000004)

RAW\_DATA\_Z

Added in API level 1

int RAW\_DATA\_Z

This constant was deprecated in API level 3.

use Sensor instead.

Index of the untransformed Z value in the array returned by onSensorChanged(int, float[])

Constant Value: 5 (0x00000005)

#### SENSOR\_ACCELEROMETER

int SENSOR\_ACCELEROMETER

This constant was deprecated in API level 3.

use Sensor instead.

A constant describing an accelerometer. See SensorListener for more details.

Constant Value: 2 (0x00000002)

#### SENSOR\_ALL

int SENSOR\_ALL

This constant was deprecated in API level 3.

use Sensor instead.

A constant that includes all sensors

Constant Value: 127 (0x0000007f)

Added in API level 1

SENSOR\_DELAY\_FASTEST

Added in API level 1

int SENSOR\_DELAY\_FASTEST

get sensor data as fast as possible

Constant Value: 0 (0x00000000)

#### SENSOR\_DELAY\_GAME

int SENSOR\_DELAY\_GAME

rate suitable for games

Constant Value: 1 (0x00000001)

#### SENSOR\_DELAY\_NORMAL

int SENSOR\_DELAY\_NORMAL

rate (default) suitable for screen orientation changes

Constant Value: 3 (0x00000003)

# SENSOR\_DELAY\_UI

int SENSOR\_DELAY\_UI

rate suitable for the user interface

Constant Value: 2 (0x00000002)

Added in API level 1

Added in API level 1

int SENSOR\_LIGHT

This constant was deprecated in API level 3.

use Sensor instead.

A constant describing an ambient light sensor See SensorListener for more details.

Constant Value: 16 (0x00000010)

#### SENSOR\_MAGNETIC\_FIELD

int SENSOR\_MAGNETIC\_FIELD

This constant was deprecated in API level 3.

use Sensor instead.

A constant describing a magnetic sensor See SensorListener for more details.

Constant Value: 8 (0x00000008)

#### SENSOR\_MAX

int SENSOR\_MAX

This constant was deprecated in API level 3.

use Sensor instead.

Largest sensor ID

Constant Value: 64 (0x00000040)

Added in API level 1

int SENSOR\_MIN

This constant was deprecated in API level 3.

use Sensor instead.

Smallest sensor ID

Constant Value: 1 (0x00000001)

#### SENSOR\_ORIENTATION

int SENSOR\_ORIENTATION

This constant was deprecated in API level 3.

use Sensor instead.

A constant describing an orientation sensor. See SensorListener for more details.

Constant Value: 1 (0x00000001)

#### SENSOR\_ORIENTATION\_RAW

int SENSOR\_ORIENTATION\_RAW

This constant was deprecated in API level 3.

use Sensor instead.

A constant describing an orientation sensor. See SensorListener for more details.

Constant Value: 128 (0x00000080)

Added in API level 1

int SENSOR\_PROXIMITY

This constant was deprecated in API level 3.

use Sensor instead.

A constant describing a proximity sensor See SensorListener for more details.

Constant Value: 32 (0x00000020)

#### SENSOR\_STATUS\_ACCURACY\_HIGH

int SENSOR\_STATUS\_ACCURACY\_HIGH

This sensor is reporting data with maximum accuracy

Constant Value: 3 (0x00000003)

### SENSOR\_STATUS\_ACCURACY\_LOW

int SENSOR\_STATUS\_ACCURACY\_LOW

This sensor is reporting data with low accuracy, calibration with the environment is needed

Constant Value: 1 (0x00000001)

Added in API level 1

Added in API level 1

### SENSOR\_STATUS\_ACCURACY\_MEDIUM

This sensor is reporting data with an average level of accuracy, calibration with the environment may improve the readings

Constant Value: 2 (0x00000002)

### SENSOR\_STATUS\_NO\_CONTACT

Added in API level 20

int SENSOR\_STATUS\_NO\_CONTACT

The values returned by this sensor cannot be trusted because the sensor had no contact with what it was measuring (for example, the heart rate monitor is not in contact with the user).

Constant Value: -1 (0xffffffff)

#### SENSOR\_STATUS\_UNRELIABLE

Added in API level 1

int SENSOR\_STATUS\_UNRELIABLE

The values returned by this sensor cannot be trusted, calibration is needed or the environment doesn't allow readings

Constant Value: 0 (0x00000000)

# SENSOR\_TEMPERATURE

Added in API level 1

int SENSOR\_TEMPERATURE

This constant was deprecated in API level 3.

use Sensor instead.

A constant describing a temperature sensor See SensorListener for more details.

Constant Value: 4 (0x00000004)

### SENSOR\_TRICORDER

Added in API level 1

int SENSOR\_TRICORDER

This constant was deprecated in API level 3.

use Sensor instead.

A constant describing a Tricorder See SensorListener for more details.

Constant Value: 64 (0x00000040)

### STANDARD\_GRAVITY

Added in API level 1

float STANDARD\_GRAVITY

Standard gravity (g) on Earth. This value is equivalent to 1G

Constant Value: 9.80665

#### Public methods

Cancels receiving trigger events for a trigger sensor.

Note that a Trigger sensor will be auto disabled if on Trigger (Trigger Event) has triggered. This method is provided in case the user wants to explicitly cancel the request to receive trigger events.

| Parameters |   |
|------------|---|
| listener   | TriggerEventListener: The listener on which the onTrigger(TriggerEvent) is delivered. It should be the same as the one used in requestTriggerSensor(TriggerEventListener, Sensor) |
| sensor     | Sensor: The sensor for which the trigger request should be canceled. If null, it cancels receiving trigger for all sensors associated with the listener.                          |

| Returns |                                |
|---------|--------------------------------|
| boolean | true if successfully canceled. |

| Throws                   |                                  |  |
|--------------------------|----------------------------------|--|
| IllegalArgumentException | when sensor is a trigger sensor. |  |

flush
Added in API level 19

boolean flush (SensorEventListener listener)

Flushes the FIFO of all the sensors registered for this listener. If there are events in the FIFO of the sensor, they are returned as if the maxReportLantecy of the FIFO has expired. Events are returned in the usual way through the SensorEventListener. This call doesn't affect the maxReportLantecy for this sensor. This call is asynchronous and returns immediately. onFlushCompleted is called after all the events in the batch at the time of calling this method have been delivered successfully. If the hardware doesn't support flush, it still returns true and a trivial flush complete event is sent after the current event for all the clients registered for this sensor.

#### Parameters

| 1 | Ιi | S | t | ρ | n | ρ | r |
|---|----|---|---|---|---|---|---|
|   |    |   |   |   |   |   |   |

SensorEventListener: A SensorEventListener object which was previously used in a registerListener call.

boolean

true if the flush is initiated successfully on all the sensors registered for this listener, false if no sensor is previously registered for this listener or flush on one of the sensors fails.

#### Throws

IllegalArgumentException

when listener is null.

#### See also:

registerListener(SensorEventListener, Sensor, int, int)

### getAltitude

Added in API level 9

Computes the Altitude in meters from the atmospheric pressure and the pressure at sea level.

Typically the atmospheric pressure is read from a TYPE\_PRESSURE sensor. The pressure at sea level must be known, usually it can be retrieved from airport databases in the vicinity. If unknown, you can use PRESSURE\_STANDARD\_ATMOSPHERE as an approximation, but absolute altitudes won't be accurate.

To calculate altitude differences, you must calculate the difference between the altitudes at both points. If you don't know the altitude as sea level, you can use PRESSURE\_STANDARD\_ATMOSPHERE instead, which will give good results considering the range of pressure typically involved.

float altitude\_difference = getAltitude(SensorManager.PRESSURE\_STANDARD\_ATMOSPHERE, pressure\_at\_point2) - getAltitude(SensorManager.PRESSURE\_STANDARD\_ATMOSPHERE, pressure\_at\_point1);

#### Parameters

p0

float: pressure at sea level

p float: atmospheric pressure

| Returns |                    |
|---------|--------------------|
| float   | Altitude in meters |

getAngleChange

Helper function to compute the angle change between two rotation matrices. Given a current rotation matrix (R) and a previous rotation matrix (prevR) computes the intrinsic rotation around the z, x, and y axes which transforms prevR to R. outputs a 3 element vector containing the z, x, and y angle change at indexes 0, 1, and 2 respectively.

Each input matrix is either as a 3x3 or 4x4 row-major matrix depending on the length of the passed array:

If the array length is 9, then the array elements represent this matrix

```
/ R[0] R[1] R[2] \
| R[3] R[4] R[5] |
\ R[6] R[7] R[8] /
```

If the array length is 16, then the array elements represent this matrix

```
/ R[ 0]
          R[ 1]
                  R[ 2]
                         R[ 3] \
  R[ 4]
          R[ 5]
                 R[ 6]
                         R[ 7] |
                         R[11] |
  R[ 8]
          R[ 9]
                  R[10]
\ R[12]
          R[13]
                  R[14]
                         R[15] /
```

See getOrientation(float[], float[]) for more detailed definition of the output.

| angleChange | float: an an array of floats (z, x, and y) in which the angle change (in radians) is stored |
|-------------|---|
| R           | float: current rotation matrix  |
| prevR       | float: previous rotation matrix   |

### getDefaultSensor

Added in API level 3

Sensor getDefaultSensor (int type)

Use this method to get the default sensor for a given type. Note that the returned sensor could be a composite sensor, and its data could be averaged or filtered. If you need to access the raw sensors use getSensorList.

| Parame | Parameters                |  |
|--------|---------------------------|--|
| type   | int: of sensors requested |  |

| Returns |  |
|---------|--|
| Sensor  | the default sensor matching the requested type if one exists and the application has the necessary permissions, or null otherwise. |

#### See also:

getSensorList(int)

Sensor

### getDefaultSensor

Added in API level 21

Sensor getDefaultSensor (int type, boolean wakeUp)

Return a Sensor with the given type and wakeUp properties. If multiple sensors of this type exist, any one of them may be returned.

For example,

- getDefaultSensor(TYPE\_ACCELEROMETER, true) returns a wake-up accelerometer sensor if it exists.
- getDefaultSensor(TYPE\_PROXIMITY, false) returns a non wake-up proximity sensor if it exists.
- getDefaultSensor(TYPE\_PROXIMITY, true) returns a wake-up proximity sensor which is the same as the Sensor returned by getDefaultSensor(int).

Note: Sensors like TYPE\_PROXIMITY and TYPE\_SIGNIFICANT\_MOTION are declared as wake-up sensors by default.

| Paramete | rs   |
|----------|--|
| type     | int: type of sensor requested  |
| wakeUp   | boolean: flag to indicate whether the Sensor is a wake-up or non wake-up sensor. |

| Returns | Returns   |  |  |
|---------|---|--|--|
| Sensor  | the default sensor matching the requested type and wakeUp properties if one exists and the application has the necessary permissions, |  |  |
|         | or null otherwise.  |  |  |

#### See also:

isWakeUpSensor()

#### getDynamicSensorList

Added in API level 24

List<Sensor> getDynamicSensorList (int type)

Use this method to get a list of available dynamic sensors of a certain type. Make multiple calls to get sensors of different types or use Sensor.TYPE\_ALL to get all dynamic sensors.

NOTE: Both wake-up and non wake-up sensors matching the given type are returned. Check is Wake UpSensor() to know the wake-up properties of the returned Sensor.

#### Parameters

type int: of sensors requested

Added in API level 3

Returns

List<Sensor>

a list of dynamic sensors matching the requested type.

See also:

Sensor

#### getInclination

float getInclination (float[] I)

Computes the geomagnetic inclination angle in radians from the inclination matrix I returned by getRotationMatrix(float[], float[], float[]).

#### Parameters

I float: inclination matrix see getRotationMatrix(float[], float[], float[]).

Returns

float

The geomagnetic inclination angle in radians.

#### See also:

getRotationMatrix(float[], float[], float[])

getOrientation(float[], float[])

GeomagneticField

getOrientation Added in API level 3

Computes the device's orientation based on the rotation matrix.

When it returns, the array values are as follows:

- values[0]: Azimuth, angle of rotation about the -z axis. This value represents the angle between the device's y axis and the magnetic north pole. When facing north, this angle is 0, when facing south, this angle is  $\pi$ . Likewise, when facing east, this angle is  $\pi/2$ , and when facing west, this angle is  $\pi/2$ . The range of values is  $\pi/2$ .
- values[1]: *Pitch*, angle of rotation about the x axis. This value represents the angle between a plane parallel to the device's screen and a plane parallel to the ground. Assuming that the bottom edge of the device faces the user and that the screen is face-up, tilting the top edge of the device toward the ground creates a positive pitch angle. The range of values is -π to π.
- values[2]: *Roll*, angle of rotation about the y axis. This value represents the angle between a plane perpendicular to the device's screen and a plane perpendicular to the ground. Assuming that the bottom edge of the device faces the user and that the screen is face-up, tilting the left edge of the device toward the ground creates a positive roll angle. The range of values is -π/2 to π/2.

Applying these three rotations in the azimuth, pitch, roll order transforms an identity matrix to the rotation matrix passed into this method. Also, note that all three orientation angles are expressed in **radians**.

| Parameters |  |
|------------|--|
| R          | float: rotation matrix see getRotationMatrix(float[], float[], float[]). |
| values     | float: an array of 3 floats to hold the result.                          |

| Returns |                                      |
|---------|--------------------------------------|
| float[] | The array values passed as argument. |

#### See also:

getRotationMatrix(float[], float[], float[], float[])

GeomagneticField

Helper function to convert a rotation vector to a normalized quaternion. Given a rotation vector (presumably from a ROTATION\_VECTOR sensor), returns a normalized quaternion in the array Q. The quaternion is stored as [w, x, y, z]

| Parameters |   |
|------------|---|
| Q          | float: an array of floats in which to store the computed quaternion |
| rv         | float: the rotation vector to convert                               |

#### getRotationMatrix

Added in API level 3

Computes the inclination matrix **I** as well as the rotation matrix **R** transforming a vector from the device coordinate system to the world's coordinate system which is defined as a direct orthonormal basis, where:

- X is defined as the vector product Y.Z (It is tangential to the ground at the device's current location and roughly points East).
- Y is tangential to the ground at the device's current location and points towards the magnetic North Pole.
- Z points towards the sky and is perpendicular to the ground.

World coordinate-system diagram.

By definition:

[0 0 g] = R \* gravity (g = magnitude of gravity)

```
[0 m 0] = I * R * geomagnetic (m = magnitude of geomagnetic field)
```

**R** is the identity matrix when the device is aligned with the world's coordinate system, that is, when the device's X axis points toward East, the Y axis points to the North Pole and the device is facing the sky.

I is a rotation matrix transforming the geomagnetic vector into the same coordinate space as gravity (the world's coordinate space). I is a simple rotation around the X axis. The inclination angle in radians can be computed with getInclination(float[]).

Each matrix is returned either as a 3x3 or 4x4 row-major matrix depending on the length of the passed array:

#### If the array length is 16:

```
/ M[ 0]
         M[ 1]
                M[2]
                       M[ 3] \
 M[ 4]
        M[ 5]
                M[ 6]
                       M[ 7] |
 M[ 8]
        M[ 9]
               M[10]
                       M[11]
\ M[12]
                       M[15] /
        M[13]
                M[14]
```

This matrix is ready to be used by OpenGL ES's glLoadMatrixf(float[], int).

Note that because OpenGL matrices are column-major matrices you must transpose the matrix before using it. However, since the matrix is a rotation matrix, its transpose is also its inverse, conveniently, it is often the inverse of the rotation that is needed for rendering; it can therefore be used with OpenGL ES directly.

Also note that the returned matrices always have this form:

```
/ M[0] M[1] M[2] 0 \
| M[4] M[5] M[6] 0 |
| M[8] M[9] M[10] 0 |
\ 0 0 0 1 /
```

#### If the array length is 9:

```
/ M[0] M[1] M[2] \
| M[3] M[4] M[5] |
\ M[6] M[7] M[8] /
```

The inverse of each matrix can be computed easily by taking its transpose.

The matrices returned by this function are meaningful only when the device is not free-falling and it is not close to the magnetic north. If the device is accelerating, or placed into a strong magnetic field, the returned matrices may be inaccurate.

| Parameters  | Parameters  |  |
|-------------|---|--|
| R           | float: is an array of 9 floats holding the rotation matrix <b>R</b> when this function returns. R can be null.  |  |
| I           | float: is an array of 9 floats holding the rotation matrix I when this function returns. I can be null.   |  |
| gravity     | float: is an array of 3 floats containing the gravity vector expressed in the device's coordinate. You can simply use the values returned by a SensorEvent of a Sensor of type TYPE_ACCELEROMETER.      |  |
| geomagnetic | float: is an array of 3 floats containing the geomagnetic vector expressed in the device's coordinate. You can simply use the values returned by a SensorEvent of a Sensor of type TYPE_MAGNETIC_FIELD. |  |

| Returns |  |
|---------|--|
| boolean | true on success, false on failure (for instance, if the device is in free fall). Free fall is defined as condition when the magnitude of the |
|         | gravity is less than 1/10 of the nominal value. On failure the output matrices are not modified.   |

#### See also:

getInclination(float[])

getOrientation(float[], float[])

remapCoordinateSystem(float[], int, int, float[])

### getRotation Matrix From Vector

Added in API level 9

Helper function to convert a rotation vector to a rotation matrix. Given a rotation vector (presumably from a ROTATION\_VECTOR sensor), returns a 9 or 16 element rotation matrix in the array R. R must have length 9 or 16. If R.length == 9, the following matrix is returned:

```
/ R[0] R[1] R[2] \
| R[3] R[4] R[5] |
\ R[6] R[7] R[8] /
```

If R.length == 16, the following matrix is returned:

```
/ R[0] R[1] R[2] 0 \
| R[4] R[5] R[6] 0 |
| R[8] R[9] R[10] 0 |
\ 0 0 0 1 /
```

| Parameters     | Parameters  |  |  |
|----------------|---|--|--|
| R              | float: an array of floats in which to store the rotation matrix |  |  |
| rotationVector | float: the rotation vector to convert                           |  |  |

getSensorList Added in API level 3

List<Sensor> getSensorList (int type)

Use this method to get the list of available sensors of a certain type. Make multiple calls to get sensors of different types or use Sensor.TYPE\_ALL to get all the sensors.

NOTE: Both wake-up and non wake-up sensors matching the given type are returned. Check is Wake Up Sensor() to know the wake-up properties of the returned Sensor.

| Parame | Parameters                |  |
|--------|---------------------------|--|
| type   | int: of sensors requested |  |

| Returns                | Returns                                    |  |
|------------------------|--|--|
| List <sensor></sensor> | a list of sensors matching the asked type. |  |

getDefaultSensor(int)

Sensor

getSensors Added in API level 1

int getSensors ()

This method was deprecated in API level 3.

This method is deprecated, use getSensorList(int) instead

#### Returns

int

available sensors.

## isDynamicSensorDiscoverySupported

Added in API level 24

boolean isDynamicSensorDiscoverySupported ()

Tell if dynamic sensor discovery feature is supported by system.

|    | Δ | ŧΠ | ľ | n | e |
|----|---|----|---|---|---|
| LX | u | U. | ш | ш | 0 |

boolean

true if dynamic sensor discovery is supported, false otherwise.

# registerDynamicSensorCallback

Add a DynamicSensorCallback to receive dynamic sensor connection callbacks. Repeat registration with the already registered callback object will have no additional effect.

| Parameter | Parameters  |  |  |
|-----------|---|--|--|
| callback  | SensorManager.DynamicSensorCallback: An object that implements the DynamicSensorCallback interface for receiving callbacks. |  |  |

| Throws                   |                        |
|--------------------------|------------------------|
| IllegalArgumentException | when callback is null. |

### See also:

ERROR(/#addDynamicSensorCallback(DynamicSensorCallback, Handler))

# $register {\tt Dynamic Sensor Callback}$

Added in API level 24

void registerDynamicSensorCallback (SensorManager.DynamicSensorCallback callback, Handler handler)

Add a DynamicSensorCallback to receive dynamic sensor connection callbacks. Repeat registration with the already registered callback object will have no additional effect.

| Parameters |   |
|------------|---|
| callback   | SensorManager.DynamicSensorCallback: An object that implements the DynamicSensorCallback interface for receiving callbacks. |
| handler    | Handler: The Handler the sensor connection events will be delivered to.   |

| Throws                   |                        |
|--------------------------|------------------------|
| IllegalArgumentException | when callback is null. |

registerListener Added in API level 3

Registers a SensorEventListener for the given sensor at the given sampling frequency.

The events will be delivered to the provided SensorEventListener as soon as they are available. To reduce the power consumption, applications can use registerListener(SensorEventListener, Sensor, int, int) instead and specify a positive non-zero maximum reporting latency.

In the case of non-wake-up sensors, the events are only delivered while the Application Processor (AP) is not in suspend mode. See isWakeUpSensor() for more details. To ensure delivery of events from non-wake-up sensors even when the screen is OFF, the application registering to the sensor must hold a partial wake-lock to keep the AP awake, otherwise some events might be lost while the AP is asleep. Note that although events might be lost while the AP is asleep, the sensor will still consume power if it is not explicitly deactivated by the application. Applications must unregister their SensorEventListeners in their activity's onPause() method to avoid consuming power while the device is inactive. See registerListener(SensorEventListener, Sensor, int, int) for more details on hardware FIFO (queueing) capabilities and when some sensor events might be lost.

In the case of wake-up sensors, each event generated by the sensor will cause the AP to wake-up, ensuring that each event can be delivered. Because of this, registering to a wake-up sensor has very significant power implications. Call isWakeUpSensor() to check whether a sensor is a wake-up sensor. See registerListener(SensorEventListener, Sensor, int, int) for information on how to reduce the power impact of registering to wake-up sensors.

Note: Don't use this method with one-shot trigger sensors such as TYPE\_SIGNIFICANT\_MOTION. Use requestTriggerSensor(TriggerEventListener, Sensor) instead. Use getReportingMode() to obtain the reporting mode of a given sensor.

| Parameters       | Parameters  |  |  |
|------------------|---|--|--|
| listener         | SensorEventListener: A SensorEventListener object.  |  |  |
| sensor           | Sensor: The Sensor to register to.  |  |  |
| samplingPeriodUs | int: The rate sensor events are delivered at. This is only a hint to the system. Events may be received faster or slower than the specified rate. Usually events are received faster. The value must be one of SENSOR_DELAY_NORMAL, SENSOR_DELAY_UI, SENSOR_DELAY_GAME, or SENSOR_DELAY_FASTEST or, the desired delay between events in microseconds. Specifying the delay in microseconds only works from Android 2.3 (API level 9) onwards. For earlier releases, you must use one of the SENSOR_DELAY_* constants. |  |  |

| Returns |   |
|---------|---|
| boolean | true if the sensor is supported and successfully enabled. |

registerListener(SensorEventListener, Sensor, int, Handler)

unregisterListener(SensorEventListener)

unregisterListener(SensorEventListener, Sensor)

## registerListener

Added in API level 19

Registers a SensorEventListener for the given sensor at the given sampling frequency and the given maximum reporting latency.

This function is similar to registerListener(SensorEventListener, Sensor, int) but it allows events to stay temporarily in the hardware FIFO (queue) before being delivered. The events can be stored in the hardware FIFO up to maxReportLatencyUs microseconds. Once one of the events in the FIFO needs to be reported, all of the events in the FIFO are reported sequentially. This means that some events will be reported before the maximum reporting latency has elapsed.

When maxReportLatencyUs is 0, the call is equivalent to a call to registerListener(SensorEventListener, Sensor, int), as it requires the events to be delivered as soon as possible.

When sensor.maxFifoEventCount() is 0, the sensor does not use a FIFO, so the call will also be equivalent to registerListener(SensorEventListener, Sensor, int).

Setting maxReportLatencyUs to a positive value allows to reduce the number of interrupts the AP (Application Processor) receives, hence reducing power consumption, as the AP can switch to a lower power state while the sensor is capturing the data. This is especially important when registering to wake-up sensors, for which each interrupt causes the AP to wake up if it was in suspend mode. See isWakeUpSensor() for more information on wake-up sensors.

Note: Don't use this method with one-shot trigger sensors such as TYPE\_SIGNIFICANT\_MOTION. Use requestTriggerSensor(TriggerEventListener, Sensor) instead.

| Parameters         |   |  |
|--------------------|---|--|
| listener           | SensorEventListener: A SensorEventListener object that will receive the sensor events. If the application is interested in receiving flush complete notifications, it should register with SensorEventListener2 instead.  |  |
| sensor             | Sensor: The Sensor to register to.  |  |
| samplingPeriodUs   | int: The desired delay between two consecutive events in microseconds. This is only a hint to the system. Events may be received faster or slower than the specified rate. Usually events are received faster. Can be one of SENSOR_DELAY_NORMAL, SENSOR_DELAY_UI, SENSOR_DELAY_GAME, SENSOR_DELAY_FASTEST or the delay in microseconds.                            |  |
| maxReportLatencyUs | int: Maximum time in microseconds that events can be delayed before being reported to the application. A large value allows reducing the power consumption associated with the sensor. If maxReportLatencyUs is set to zero, events are delivered as soon as they are available, which is equivalent to calling registerListener(SensorEventListener, Sensor, int). |  |

| Returns | Returns   |  |
|---------|---|--|
| boolean | true if the sensor is supported and successfully enabled. |  |

### See also:

registerListener(SensorEventListener, Sensor, int)

unregisterListener(SensorEventListener)

flush(SensorEventListener)

# registerListener

int samplingPeriodUs,
Handler handler)

Registers a SensorEventListener for the given sensor. Events are delivered in continuous mode as soon as they are available. To reduce the power consumption, applications can use registerListener(SensorEventListener, Sensor, int, int) instead and specify a positive non-zero maximum reporting latency.

Note: Don't use this method with a one shot trigger sensor such as TYPE\_SIGNIFICANT\_MOTION. Use requestTriggerSensor(TriggerEventListener, Sensor) instead.

| Parameters       |   |
|------------------|---|
| listener         | SensorEventListener: A SensorEventListener object.  |
| sensor           | Sensor: The Sensor to register to.  |
| samplingPeriodUs | int: The rate sensor events are delivered at. This is only a hint to the system. Events may be received faster or slower than the specified rate. Usually events are received faster. The value must be one of SENSOR_DELAY_NORMAL, SENSOR_DELAY_UI, SENSOR_DELAY_GAME, or SENSOR_DELAY_FASTEST or, the desired delay between events in microseconds. Specifying the delay in microseconds only works from Android 2.3 (API level 9) onwards. For earlier releases, you must use one of the SENSOR_DELAY_* constants. |
| handler          | Handler: The Handler the sensor events will be delivered to.  |

| Returns | Returns   |  |
|---------|---|--|
| boolean | true if the sensor is supported and successfully enabled. |  |

### See also:

registerListener(SensorEventListener, Sensor, int)

unregisterListener(SensorEventListener)

unregisterListener(SensorEventListener, Sensor)

registerListener Added in API level 1

### This method was deprecated in API level 3.

This method is deprecated, use registerListener(SensorEventListener, Sensor, int) instead.

Registers a listener for given sensors.

| Parameters |  |
|------------|--|
| listener   | SensorListener: sensor listener object         |
| sensors    | int: a bit masks of the sensors to register to |

| Returns |  |
|---------|--|
| boolean | true if the sensor is supported and successfully enabled |

# registerListener Added in API level 1

### This method was deprecated in API level 3.

This method is deprecated, use register Listener (Sensor Event Listener, Sensor, int) instead.

Registers a SensorListener for given sensors.

| Parameters |  |
|------------|--|
| listener   | SensorListener: sensor listener object         |
| sensors    | int: a bit masks of the sensors to register to |
|            |  |

| rate | int: rate of events. This is only a hint to the system. events may be received faster or slower than the specified rate. Usually events |
|------|---|
|      | are received faster. The value must be one of SENSOR_DELAY_NORMAL, SENSOR_DELAY_UI, SENSOR_DELAY_GAME, or                               |
|      | SENSOR_DELAY_FASTEST.   |

| Returns |  |
|---------|--|
| boolean | true if the sensor is supported and successfully enabled |

## registerListener

Added in API level 19

boolean registerListener (SensorEventListener listener,
Sensor sensor,
int samplingPeriodUs,
int maxReportLatencyUs,
Handler handler)

Registers a SensorEventListener for the given sensor at the given sampling frequency and the given maximum reporting latency.

| Parameters         |   |
|--------------------|---|
| listener           | SensorEventListener: A SensorEventListener object that will receive the sensor events. If the application is interested in receiving flush complete notifications, it should register with SensorEventListener2 instead.  |
| sensor             | Sensor: The Sensor to register to.  |
| samplingPeriodUs   | int: The desired delay between two consecutive events in microseconds. This is only a hint to the system. Events may be received faster or slower than the specified rate. Usually events are received faster. Can be one of SENSOR_DELAY_NORMAL, SENSOR_DELAY_UI, SENSOR_DELAY_GAME, SENSOR_DELAY_FASTEST or the delay in microseconds.                            |
| maxReportLatencyUs | int: Maximum time in microseconds that events can be delayed before being reported to the application. A large value allows reducing the power consumption associated with the sensor. If maxReportLatencyUs is set to zero, events are delivered as soon as they are available, which is equivalent to calling registerListener(SensorEventListener, Sensor, int). |
| handler            | Handler: The Handler the sensor events will be delivered to.  |

| Returns | Returns   |  |
|---------|---|--|
| boolean | true if the sensor is supported and successfully enabled. |  |

registerListener(SensorEventListener, Sensor, int, int)

### remapCoordinateSystem

Added in API level 3

Rotates the supplied rotation matrix so it is expressed in a different coordinate system. This is typically used when an application needs to compute the three orientation angles of the device (see <a href="mailto:getOrientation(float[]">getOrientation(float[]</a>, float[])) in a different coordinate system.

When the rotation matrix is used for drawing (for instance with OpenGL ES), it usually **doesn't need** to be transformed by this function, unless the screen is physically rotated, in which case you can use Display.getRotation() to retrieve the current rotation of the screen. Note that because the user is generally free to rotate their screen, you often should consider the rotation in deciding the parameters to use here.

### Examples:

• Using the camera (Y axis along the camera's axis) for an augmented reality application where the rotation angles are needed:

```
remapCoordinateSystem(inR, AXIS_X, AXIS_Z, outR);
```

• Using the device as a mechanical compass when rotation is Surface.ROTATION\_90:

```
remapCoordinateSystem(inR, AXIS_Y, AXIS_MINUS_X, outR);
```

Beware of the above example. This call is needed only to account for a rotation from its natural orientation when calculating the rotation angles (see getOrientation(float[], float[])). If the rotation matrix is also used for rendering, it may not need to be transformed, for instance if your Activity is running in landscape mode.

Since the resulting coordinate system is orthonormal, only two axes need to be specified.

| Param | Parameters   |  |
|-------|--|--|
| inR   | float: the rotation matrix to be transformed. Usually it is the matrix returned by getRotationMatrix(float[], float[], float[]). |  |
| X     | int: defines the axis of the new cooridinate system that coincide with the X axis of the original coordinate system.             |  |
| Υ     | int: defines the axis of the new cooridinate system that coincide with the Y axis of the original coordinate system.             |  |
| outR  | float: the transformed rotation matrix. inR and outR should not be the same array.   |  |

| Returns | Returns  |  |
|---------|--|--|
| boolean | true on success. false if the input parameters are incorrect, for instance if X and Y define the same axis. Or if inR and outR don't |  |
|         | have the same length.  |  |

getRotationMatrix(float[], float[], float[], float[])

## requestTriggerSensor

Added in API level 18

Requests receiving trigger events for a trigger sensor.

When the sensor detects a trigger event condition, such as significant motion in the case of the TYPE\_SIGNIFICANT\_MOTION, the provided trigger listener will be invoked once and then its request to receive trigger events will be canceled. To continue receiving trigger events, the application must request to receive trigger events again.

| Parameters |  |
|------------|--|
| listener   | TriggerEventListener: The listener on which the onTrigger(TriggerEvent) will be delivered. |
| sensor     | Sensor: The sensor to be enabled.  |

### Returns

| Throws                   |  |
|--------------------------|--|
| IllegalArgumentException | when sensor is null or not a trigger sensor. |

## unregisterDynamicSensorCallback

true if the sensor was successfully enabled.

Added in API level 24

void unregisterDynamicSensorCallback (SensorManager.DynamicSensorCallback callback)

Remove a DynamicSensorCallback to stop sending dynamic sensor connection events to that callback.

| Parameters | arameters   |  |
|------------|---|--|
| callback   | SensorManager.DynamicSensorCallback: An object that implements the DynamicSensorCallback interface for receiving callbacks. |  |

## unregisterListener

Added in API level 3

void unregisterListener (SensorEventListener listener)

Unregisters a listener for all sensors.

| Parameters | Parameters                                   |  |
|------------|--|--|
| listener   | SensorEventListener: a SensorListener object |  |

### See also:

boolean

unregisterListener(SensorEventListener, Sensor)

registerListener(SensorEventListener, Sensor, int)

Unregisters a listener for the sensors with which it is registered.

Note: Don't use this method with a one shot trigger sensor such as TYPE\_SIGNIFICANT\_MOTION. Use cancelTriggerSensor(TriggerEventListener, Sensor) instead.

| Parameters | Parameters  |  |
|------------|---|--|
| listener   | SensorEventListener: a SensorEventListener object |  |
| sensor     | Sensor: the sensor to unregister from             |  |

### See also:

unregisterListener(SensorEventListener)

registerListener(SensorEventListener, Sensor, int)

## unregisterListener

Added in API level 1

void unregisterListener (SensorListener listener)

This method was deprecated in API level 3.

This method is deprecated, use unregisterListener(SensorEventListener) instead.

Unregisters a listener for all sensors.

| Parameters | Parameters                              |  |
|------------|---|--|
| listener   | SensorListener: a SensorListener object |  |

### This method was deprecated in API level 3.

This method is deprecated, use unregisterListener(SensorEventListener, Sensor) instead.

Unregisters a listener for the sensors with which it is registered.

| Parameters | Parameters   |  |
|------------|--|--|
| listener   | SensorListener: a SensorListener object            |  |
| sensors    | int: a bit masks of the sensors to unregister from |  |